



Poppenbouwing 52  
4191 NZ Geldermalsen  
The Netherlands

VAT: NL007508773B01  
IBAN: NL27RABO0321200616  
SWIFT: RABONL2U  
CoC: 11018516

Date: June 26<sup>th</sup>, 2019

Subject: Silas release notes V3.10.1.0

Dear Silas user,

Silas V3.10.1.0 is now available. This release contains updated versions of both Silas Acquisition (V3.10.1.0) and Silas Processing (V3.10.1.0). Several bug fixes have been made and issues resolved. Stema has also added new functionalities to this release. If you currently have an active maintenance contract, you can download the release using the following button.

**DOWNLOAD SILAS V3.10.1.0**

If you currently are not in possession of a maintenance contract and would like to have information about this maintenance program you can contact our sales department ([sales@stema-systems.nl](mailto:sales@stema-systems.nl)).

The main new developments of this Silas release are:

- Minimized windows now go to the task bar
- New Feature: Option in the export wizard to export density layers above the water bottom
- New Feature: Descending trace order in trace window settings is now saved per line
- New Feature: Reduce data contains option to remove data below multiple of water bottom
- New Feature: Rewrite SEI contains option to export corresponding .XYD or .XYZ files
- Save picture exports files with line and project name
- The horizontal distance between depth labels is based on pixels instead of traces
- A bug in the location of Y-labels is fixed
- Functionality of Record theoretical data improved
- Improved interaction between Silas Processing and other opened programs
- Processing and Acquisition now have the same version number
- Threshold part for layer bottom in Auto tracing now set to 0.99 for new projects
- Depth information is now included in SEGY import and export
- Start/end in status bar are updated correctly and the hot keys to change them function
- If position data is not being recorded the X and Y status bar fields become red
- Settings of serial communication are saved and applied correctly



Poppenbouwing 52  
4191 NZ Geldermalsen  
The Netherlands

VAT: NL007508773B01  
IBAN: NL27RABO0321200616  
SWIFT: RABONL2U  
CoC: 11018516

We advise to always run the software as administrator. If there are still problems starting the software while running it as administrator, it might be due to active firewalls blocking the Silas software.

If you have any questions, feedback or inquiries for developments to be made, please inform us as we would gladly try and take this into account for our next release. You can send an e-mail to [support@stema-systems.nl](mailto:support@stema-systems.nl).

Stema Systems